

HID® FARGO® DTC™1500

Printer Firmware Release Notes

**Firmware Version: 3.7.0.8
PLT-06737, Rev. A.4
November 2025**



Copyright

© 2022 - 2025 HID Global Corporation/ASSA ABLOY AB. All rights reserved.

This document may not be reproduced, disseminated, or republished in any form without the prior written permission of HID Global Corporation.

Trademarks

HID GLOBAL, HID, the HID Brick logo, DTC, and FARGO are trademarks or registered trademarks of HID Global, ASSA ABLOY AB, or its affiliate(s) in the US and other countries and may not be used without permission. All other trademarks, service marks, and product or service names are trademarks or registered trademarks of their respective owners.

Contacts

For technical support, please visit: <https://support.hidglobal.com>.

What's new

Date	Description	Revision
November 2025	Release notes for version 3.7.0.8.	A.4

A complete list of revisions is available in [Revision history](#).

1.1 Scope

These release notes provide information on the HID® FARGO® DTC™1500 Printer Firmware version 3.7.0.8. Included are product enhancements, fixes, known issues, and limitations since the previous release.

Note: The reference numbers associated with these features, issues, and fixes are from the HID Global internal tracking system.

1.2 New features and product enhancements

- Added 300 x 600 DPI resin support which requires updating the driver to version (5.6.x or above). (FSA-77, FSA-85)
- Added web page enable/disable to LCD menu. (FSA2-2410)
- Added enhancements to comply with European Radio Equipment Directive - Delegated Act (RED-DA). (FSA-1408)
- Updated job encryption to be compliant with RED-DA. This requires an updated driver version (5.6.x or above).
- Added support for NextGen ribbon. (FSA-1396)

Important: If using Next Generation ribbons, please update your driver, firmware, and color profile to ensure best results. Visit <https://player.vimeo.com/video/1111075180> for step-by-step instructions.

1.3 Resolved issues

- Resolved an issue when using YMCKOKO split panel film generated error 100. (TTP-15868, FSA-987)
- Resolved an issue where a random **Ribbon RFID Error and Ribbon Miscue** (error 97) occurred after upgrading to firmware 3.3.20.1. (TTP-16000, FSA-1107)

Revision history

Date	Description	Revision
November 2025	Release notes for version 3.7.0.8.	A.4
March 2025	Release notes for version 3.3.23.2	A.3
December 2023	Release notes for version 3.3.20.1	A.2
November 2023	Release notes for version 3.3.19.1.	A.1
December 2022	Release notes for version 3.3.10.1	A.0



hidglobal.com

For technical support, please visit: <https://support.hidglobal.com>

© 2025 HID Global Corporation/ASSA ABLOY AB.

All rights reserved.

PLT-06737, Rev. A.4

Part of ASSA ABLOY